




Create a user in MSSQL

Main developer: Michele Berlato (*University of Padova*)

Contributors: Giorgio Agugiaro (*TU Delft*), Ken Arroyo Ohori (*TU Delft*), Carlo Zanchetta (*University of Padova*)




Open SQL Server Configuration Manager







Open Protocols for SQLEXPRESS and enable TCP/IP






Open TCP/IP Properties and set TCP Port 1433





Open SQL Server Services and **restart** SQL Server






SQL Server Configuration Manager



Wait





Microsoft SQL Server



Login to SQL Server (windows authentication)

Connect to Server

SQL Server

Login | Connection Properties | Always Encrypted | Additional Connection Parameters

Server

Server type: Database Engine

Server name: WINDOWS11\SQLEXPRESS

Authentication: Windows Authentication

User name: WINDOWS11\vbouser

Password:

☐ Remember password

Connection Security

Encryption: Optional


☒ Trust server certificate

Host name in certificate:

Connect Cancel Help Options <<



Create a New Login





Microsoft SQL Server



Set “SQL Server authentication” Name and Password

Login - New

Select a page

- General
- Server Roles
- User Mapping
- Securables
- Status

Script ? Help

Login name: mssql_user Search...

☐ Windows authentication

☐ Microsoft Entra ID authentication

☒ SQL Server authentication

Password:

Confirm password:

☐ Specify old password

Old password:

☒ Enforce password policy

☒ Enforce password expiration

☒ User must change password at next login

☐ Mapped to certificate

☐ Mapped to asymmetric key

☐ Map to Credential

Add

Mapped Credentials

Credential	Pro
------------	-----

Remove

Default database: master

Default language: <default>

OK Cancel

Connection

Server: Windows11\SQLEXPRESS

Connection: WINDOWS11\vbouser

[View connection properties](#)

Progress

Ready



Microsoft SQL Server



Remove “Enforce password policy”

Login - New

Select a page

- General
- Server Roles
- User Mapping
- Securables
- Status

Script ? Help

Login name: mssql_user Search...

☐ Windows authentication

☐ Microsoft Entra ID authentication

☒ SQL Server authentication

Password:

Confirm password:

☐ Specify old password

Old password:

☐ Enforce password policy

☐ Enforce password expiration

☐ User must change password at next login

☐ Mapped to certificate

☐ Mapped to asymmetric key

☐ Map to Credential

Mapped Credentials

Credential	Pro
------------	-----

Remove

Default database: master

Default language: <default>

OK Cancel

Server: Windows11\SQLEXPRESS

Connection: WINDOWS11\wboxuser


[View connection properties](#)

Progress

Ready




Set “Server Roles” as ADMIN





Set “User Mapping” for ifcSQL






Microsoft SQL Server



Open server property






Microsoft SQL Server




Enable “SQL Server and Windows Authentication mode”





Open SQL Server Services and **restart** SQL Server (again)





Microsoft SQL Server



Test if the connection works (it is essential that it works)

Connect to Server

SQL Server

Login | Connection Properties | Always Encrypted | Additional Connection Parameters

Server

Server type: Database Engine

Server name: WINDOWS11\SQLEXPRESS, 1433

Authentication: SQL Server Authentication

Login: mssql_user

Password: *****

☒ Remember password

Connection Security

Encryption: Optional

☒ Trust server certificate

Host name in certificate:

Connect Cancel Help Options <<